

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2176 Dress-sweater in winter jersey

Recommendations on fabric: thick natural/mixed knit fabric of small stretchiness.

You will also need: knit fusible interfacing, separating zipper.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve – 1.5 cm.

Main fabric:

1. Back – cut 2
2. Back yoke – cut 2
3. Front – cut 2
4. Front yoke – cut 2
5. Sleeve – cut 2
6. Back facing – cut 2
7. Front facing – cut 2

Fusible interfacing:

1. Back facing – cut 2
2. Front facing – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew darts on front, if the size implies these, press bulk towards top.
3. Sew center seam on back yoke, press towards left, serge. Sew center seam on front yoke, press towards left, serge. Sew shoulder seams, press seams towards back, serge.
4. Sew center back seam, press towards left, serge. Sew center front seam, inserting the right side of zipper between the pieces, press seam allowances to the right, serge. Sew a decorative stitch along the seam at 0.5 cm. Topstitch the left side of zipper onto Front.
5. Sew sleeves to back, press seam allowances towards sleeve and serge. Sew sleeves to front, press seam allowances towards sleeve and serge.
6. Pin yoke to the garment and sew around, press seam allowances towards yoke and serge. Sew a decorative stitch along the seam at 0.5 cm.
7. Sew side seams processing the sleeve seam at the same time, serge, and press.
8. Sew center edges of facings, sew shoulder edges of facings, press seam apart. Serge lower edge. Pin facing to garment right sides together and sew the neckline. Turn facing under, straighten, press. Slipstitch facing to the seam allowances of center and shoulder seams.
9. Seam allowance along hem of garment and hem of sleeve serge, press onto wrong side and topstitch.

Congratulations, your dress-sweater is ready! :)