

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.


2404 Dress with asymmetric slit front

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: lining, fusible interfacing, dress zipper.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm; seam allowance for hem of dress – 3 cm, seam allowance for hem of sleeve – 1.5 cm.

Main fabric:

1. Upper center back - cut 2
2. Upper side back - cut 2
3. Lower center back - cut 2
4. Lower side back - cut 2
5. Upper center front - cut 1
6. Upper side front - cut 2
7. Right lower front – cut 1
8. Left lower front – cut 1
9. Fly piece – cut 1

10. Sleeve – cut 2

Lining:

1. Upper center back - cut 2
2. Upper side back - cut 2
3. Lower center back - cut 2
4. Lower side back - cut 2
5. Upper center front - cut 1
6. Upper side front - cut 2
7. Right lower front – cut 1
8. Left lower front – cut 1
9. Fly piece – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing to back neckline, front neckline, slanted edges of lower fronts.
2. Sew princess seams on upper back and on upper front, press towards center. Sew side seams and shoulder seams on upper part, press seam apart.
3. Sew seams on upper part of lining, press seam apart. Pin lining to garment right sides together and sew the neckline. Clip into curves, turn the piece right side out, straighten, press. Baste lining to garment along all edges.
4. Pin right lower front to lining right sides together and sew the slanted edge. Clip into curves, turn the piece right side out, straighten, press. Pin left lower front to lining right sides together and sew the slanted edge, turn the piece right side out, straighten, press. Pin fly piece to lining right sides together and sew the slanted and lower edges. Turn the piece right side out, straighten, press.
5. Sew lower side backs to lower fronts, press seam allowances towards back. Pin right lower front onto left lower front, pin fly piece onto right front, baste together all pieces along the waist edge. Sew princess seams on lower backs, press towards center.
6. Sew the princess and side edges on lower parts of lining, press seams towards back. Baste lower lining to the pieces from main fabric along the waist edge and back center edge. Topstitch right skirt onto left skirt along the marked line.
7. Sew upper part to lower part, press towards top and serge.
8. Serge center back edges separately on each piece. Sew center back seam from notch to



Model 2404

pattern from pppp.dk

bottom edge, press seam apart. Sew in zipper.

Congratulations, your dress is ready! :)