

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2445 Vest with asymmetrical collar

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: lining; fusible interfacing; 3 buttons; 1 inner button.



CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams 1 cm. Seam allowance for hem 2 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front – cut 2
5. Collar - cut 2
6. Center front facing – cut 2
7. Back neck facing – cut 1

Lining:

1. Center back – cut 2
2. Side back – cut 2

3. Side front – cut 2
4. Center front – cut 2

Fusible interfacing:

1. Center front facing – cut 2
2. Back neck facing – cut 1
3. Collar - cut 1

Pieces from lining are cut using the pattern blocks for main fabric, except for the width of back neckline facing and center front facing.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side backs to center back. Press towards center. Sew center back seam. Press seam apart.
3. Sew side fronts to front. Press towards center.
4. Sew shoulder and side edges of the waistcoat. Press seam apart.
5. Pin upper collar to lower collar and sew along outer edge. Clip into curves. Turn the collar right side out, straighten and press.
6. Sew and press apart shoulder seams of back neckline facing and buttonstand.
7. Place center front facing onto front right sides together, pin together and sew along the center front edge and neckline, inserting collar. Turn center front facings right side out, clip into seam allowances and straighten.
8. Sew seams on lining, leaving an opening in left side seam. Sew lining to button stands (center front facings) and to back neckline facing. Sew armhole in two steps: first sew front armhole, then sew back armhole. Clip seam allowances and press. Fold the seam allowance for hem of vest upwards, and press. Sew lining along lower edge. Turn the vest right side out through the opening. Sew the opening closed.
9. Make buttonholes on right front, sew on buttons on left front. Make buttonhole for inner button on the left front. Sew on inner button.

Congratulations, your vest is ready! :)