

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 2745 Fitted dress with triangle neckline and collar

Recommendations on fabric: natural/mixed fabric suitable for dresses approx. 1.5 m (size 32-42), approx. 2 m (size 44-54) with a fabric width of 150 cm.

You will also need: fusible interfacing, dress zipper.

### CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm, seam allowance for hem of garment – 2 cm.

### Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Center front - cut 1 on fold
4. Side front - cut 2
5. Sleeve – cut 2
6. Back neck facing – cut 2
7. Front neck facing – cut 1
8. Collar – cut 4

## 9. Cuff - cut 2

### Fusible interfacing:

1. Back neck facing – cut 2
2. Front neck facing – cut 1
3. Collar – cut 2
4. Cuff – cut 2

### INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side back pieces to the center back, press seam allowances towards the center, and serge.
3. Serge each center back edge separately. Sew the center back seam from the zipper marking down to the lower edge, then press the seam open. Insert the zipper.
4. Sew side fronts to the front, press seam allowances towards the center, and serge.
5. Sew side and shoulder seams, press towards the back, and serge.
6. Pin collar pairs together with right sides facing, then sew the collar ends and collar fall. Trim seam allowances, turn the collars right side out, straighten, and press.
7. Sew the shoulder seams of the neckline facings, pressing the seams open. Serge the outer edge. Pin the facing to the garment with right sides together and sew along the neckline, inserting the collars. Clip curves, clip the corner at the front, then turn the facings to the wrong side and press. Slipstitch the facings to the shoulder seams and the zipper tape.
8. Sew the sleeve seam, press towards the back, and serge. Sew the cuff into a ring and press the seam open. Fold the cuff in half lengthwise with the right side out and press. Sew the cuff from the wrong side, then serge. Fold the cuff to the right side and baste it along the sleeve seam. Sew the sleeves into the armholes, serge, and press.
9. Serge the bottom edge of the dress, fold it to the wrong side, and topstitch.

Congratulations, your dress is ready! :)