

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.


Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5575 Classic beret for women

Recommendations on fabric: eco leather or coat fabric approx. 0.4 m with a fabric width of 150 cm.

You will also need: Lining approx. 0.3 m with a fabric width of 150 cm.



CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams 1 cm, all edges of tube - 0 cm.

Main fabric:

1. Gore - 6 pieces
2. Band - 1 piece
3. Tube - 1 piece

Lining:

1. Gore - 6 pieces
2. Bias trimming - 1 piece

INSTRUCTIONS:

1. Sew gores together by two, right sides together. Sew one more gore to each pair of gores.
2. Fold longer edges of tube under onto the wrong side, matching the center, fold in half lengthwise, and topstitch at 0.1. - 0.2. cm from the edge.
3. Baste tube to one of the halves of the cap. Fold gores together, matching them exactly at the center, and sew central seam, sewing the tube at the same time.
4. Sew lining in the same way as the self. Place lining inside the cap, slipstitch lining to self along the seams.
5. Sew band into a ring, press apart and topstitch seam allowances on both sides of the seam. Fold band in half lengthwise wrong side together and topstitch lengthwise, making parallel stitches at 0.5 - 0.6 cm from each other.
6. Pin band to cap right sides together, baste band to cap, adjusting ease. Pin bias trimming cut of lining from the band side. Sew. Fold bias trimming onto wrong side, fold under and stitch in the ditch.

Congratulations, your beret is ready! :)