

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5982 Dress with drapery

Recommendations on fabric: well draping, medium stretch knit fabric.

You will also need: fusible interfacing.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: hem, hem of sleeve, lower and slant edges of draping – 1.5 cm, all other seams - 1 cm.

Main fabric:

1. Back – cut 2
2. Front – cut 1 on fold
3. Sleeve – cut 2
4. Front neck facing – cut 2
5. Back neck facing – cut 2
6. Front drape - cut 1 on fold



Fusible interfacing:

1. Front neck facing — cut 2
2. Back neck facing — cut 2

INSTRUCTIONS:

Advice: Knit fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hem is stitched with twin needles to save stretchiness. Pieces can also be sewn together with 3 or 4 – thread serger. When serging, cut seam allowances to 0.6 – 0.8 cm.

1. Sew darts on front. Press toward hem. Sew center edge of back. Serge and press toward left.
2. Serge slant sides and lower edge of the draping, turn inside and topstitch. Make a gathering stitch on top edge of the draping and gather. Turn inside slant (finished) edge of the draping near top edge of the draping at 1.5 cm. Stitch the draping to upper edge of front. Tack front and draping along side seams. Consider that lower edge on draping is turned inside.
3. Sew side seams, serge and press towards back part.
4. Serge lower edge of armhole on garment. Gather fullness on the sleeve to fit along raglan line of back and front. Sew sleeve to back and to front. Press seam allowance toward garment. Clip seam allowance on back / front armhole near the notch. Press under bottom edge of armhole on garment and topstitch.
5. Apply interfacing to facings. Sew each set of front and back neck facings at side edges. Press seam apart. Place facings right sides together and sew inner edge. Turn right side out and press. Stitch lower facing to neck edge. Press seam towards facing. Press outer edge of top facing under to 1 cm and topstitch into lower facing connecting seam.
6. Serge hem of garment and lower edge of the armhole. Turn under, press, and topstitch.

Congratulations, your dress is ready! :)