

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.


2357 Blouse with batwing sleeves and wrinkles

Recommendations on fabric:
natural/mixed fabrics suitable for blouses. Fabrics with stripes are recommended.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece.

Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Main fabric:

1. Back - cut 1 on fold
2. Front - cut 1 on fold
3. Front yoke - cut 1 on fold
4. Back yoke - cut 1 on fold
5. Cuff - cut 2

INSTRUCTIONS:

1. Sew a gathering stitch along the upper edge of front between the marks and gather

fullness. Arrange the gathers so that most of them are closer to center. Sew front yoke to front. Serge and press towards top.

2. Sew a gathering stitch along the upper edge of back between the marks and gather fullness. Arrange the gathers so that most of them are closer to center. Sew back yoke to yoke. Serge and press towards top.

3. Sew right shoulder seam, press seams towards back and serge.

4. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of neckline + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to neckline from the right side and sew. Clip seam allowances. Fold bias tape onto wrong side and topstitch onto main piece along seam. Press seam.

5. Sew right shoulder seam, press seam allowance towards back and serge.

6. Sew side seams, processing the sleeve seam at the same time. Press seams towards back and serge.

7. Sew cuff into a ring. Press seam apart. Fold cuff in half lengthwise and press right side out. Sew a gathering stitch along the open edge and gather fullness. Sew cuff to sleeve. Serge and press onto sleeve.

8. Serge bottom edge of garment, press onto wrong side and topstitch.

Congratulations, your blouse is ready! :)